# JoystickState Structure (Microsoft.DirectX.DirectInput)

Article11/06/2009

Describes the state of a joystick device. This structure is used with the Inputdevice9Getdevicestate method.

### Definition

	C Expand table
Visual Basic	Public Structure <b>JoystickState</b>
C#	public struct JoystickState
C++	public value class JoystickState sealed
JScript	In JScript, you can use structures, but you cannot define your own.

### **Members Table**

The following table lists the members exposed by the object.

### Methods

**Expand table** 

Method	Description
GetASlider	Extra axis accelerations.
GetButtons	Array of buttons. The high-order bit of the byte is set if the corresponding button is down, and clear if the button is up or does not exist.
GetFSlider	Extra axis forces.
GetPointOfView	Direction controllers, such as point-of-view hats. The position is indicated in hundredths of a degree clockwise from north (away from the user). The center position is normally reported as -1; but see Remarks. For indicators that have only five positions, the value for a controller is -1, 0, 9,000, 18,000, or 27,000.
GetSlider	Two additional axes, formerly called the u-axis and v-axis, whose semantics depend on the joystick. Use the Inputdevice9Getobjectinfo method to obtain semantic information about these values.

Method	Description
GetVSlider	Extra axis velocities.
JoystickState	Initializes a new instance of the object.
ToString	Obtains a string representation of the current instance.

# **Properties**

## **Expand table**

Property	Description
ARx	X-axis angular acceleration.
ARy	Y-axis angular acceleration.
ARz	Z-axis angular acceleration.
AX	X-axis acceleration.
AY	Y-axis acceleration.
AZ	Z-axis acceleration.
FRx	X-axis torque.
FRy	Y-axis torque.
FRz	Z-axis torque.
FX	X-axis force.
FY	Y-axis force.
FZ	Z-axis force.
Rx	X-axis rotation. If the joystick does not have this axis, the value is 0.
Ry	Y-axis rotation. If the joystick does not have this axis, the value is 0.
Rz	Z-axis rotation (often called the rudder). If the joystick does not have this axis, the value is 0.
VRx	X-axis angular velocity.
VRy	Y-axis angular velocity.
VRz	Z-axis angular velocity.
VX	X-axis velocity.

Property	Description
VY	Y-axis velocity.
VZ	Z-axis velocity.
X	X-axis, usually the left-right movement of a stick.
Υ	Y-axis, usually the forward-backward movement of a stick.
Z	Z-axis, often the throttle control. If the joystick does not have this axis, the value is 0.

## **Structure Information**

## **Expand table**

Namespace	Microsoft.DirectX.DirectInput
Assembly	Microsoft.DirectX.DirectInput (microsoft.directx.directinput.dll)
Strong Name	Microsoft.DirectX.DirectInput, Version=1.0.900.0, Culture=neutral, PublicKeyToken=d3231b57b74a1492